DeltaRobot

v0.1

Generated by Doxygen 1.8.9.1

Mon Mar 9 2015 21:04:06

Contents

1	Hiera	erarchical Index				
	1.1	Class Hierarchy	1			
2	Clas	s Index	3			
	2.1	Class List	3			
3	Clas	ss Documentation				
	3.1	AX12 Class Reference	5			
	3.2	data Struct Reference	5			
	3.3	dxl_hal Class Reference	5			
	3.4	dynamixel Class Reference	6			
	3.5	dynamixel2 Class Reference	6			
	3.6	XJoystick::Info Struct Reference	7			
		3.6.1 Detailed Description	7			
	3.7	MainWindow Class Reference	8			
	3.8	OptionsServos Class Reference	8			
	3.9	OptionsWindow Class Reference	8			
	3.10	ping_data Struct Reference	9			
	3.11	XJoystick Class Reference	9			
		3.11.1 Detailed Description	10			
		3.11.2 Member Function Documentation	10			
		3.11.2.1 current	10			
Ind	dex		11			

Chapter 1

Hierarchical Index

1.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

data	5
data	5
dynamixel	6
dynamixel2	6
XJoystick::Info	7
ping_data	9
QDialog	
OptionsWindow	. 8
QMainWindow	
MainWindow	. 8
QObject	
AX12	
XJoystick	. 9
QWidget	
OptionsServos	. 8

2 **Hierarchical Index**

Chapter 2

Class Index

2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

AX12
Used to control AX-12 motors from Dynamixel
data
dxl_hal
dynamixel
dynamixel2 6
XJoystick::Info
Struct to handle the info
MainWindow
OptionsServos
OptionsWindow
ping_data 9
XJoystick
The XJoystick's class is used to control the SFML Joystick's class with signals and slots

Class Index

Chapter 3

Class Documentation

3.1 AX12 Class Reference

The AX12 class is used to control AX-12 motors from Dynamixel.

#include <ax12.h>

Inheritance diagram for AX12:

3.2 data Struct Reference

Public Attributes

- · unsigned char iID
- unsigned int iStartAddr
- · unsigned short iLength
- unsigned char iError
- unsigned char * pucTable

The documentation for this struct was generated from the following file:

· dynamixel.h

3.3 dxl_hal Class Reference

Public Member Functions

- int open (QString &devName, int baudrate)
- void close (void)
- void clear (void)
- int change_baudrate (float baudrate)
- int write (unsigned char *pPacket, int numPacket)
- int read (unsigned char *pPacket, int numPacket)
- double **get_curr_time** ()
- bool isOpen ()

The documentation for this class was generated from the following files:

- dxl_hal.h
- dxl_hal.cpp

6 Class Documentation

3.4 dynamixel Class Reference

Public Member Functions

- bool isOpen ()
- int initialize (QString port_num, int baud_rate)
- int change_baudrate (int baud_rate)
- int terminate (void)
- int get comm result (void)
- void tx_packet (void)
- void rx_packet (void)
- void txrx_packet (void)
- void set_txpacket_id (int id)
- void set_txpacket_instruction (int instruction)
- void set_txpacket_parameter (int index, int value)
- void set_txpacket_length (int length)
- int get_rxpacket_error (int error)
- int get_rxpacket_error_byte (void)
- int get_rxpacket_parameter (int index)
- int get_rxpacket_length ()
- void **ping** (int id)
- int read byte (int id, int address)
- void write_byte (int id, int address, int value)
- int read_word (int id, int address)
- · void write word (int id, int address, int value)
- double get_packet_time ()
- void set_packet_timeout (int NumRcvByte)
- void set_packet_timeout_ms (int msec)
- int is_packet_timeout ()

The documentation for this class was generated from the following files:

- · dynamixel.h
- dynamixel.cpp

3.5 dynamixel2 Class Reference

Public Member Functions

- bool isOpen ()
- int initialize (QString port_num, int baud_rate)
- int change_baudrate (int baud_rate)
- int terminate (void)
- int get comm result (void)
- void tx_packet (void)
- void rx_packet (void)
- void txrx_packet (void)
- void set_txpacket_id (unsigned char id)
- · void set_txpacket_instruction (unsigned char instruction)
- void set txpacket parameter (unsigned short index, unsigned char value)
- void set_txpacket_length (unsigned short length)
- int get_rxpacket_error_byte (void)
- int get_rxpacket_parameter (int index)

- int get_rxpacket_length ()
- void **ping** (unsigned char id)
- int get_ping_result (unsigned char id, int info_num)
- void broadcast_ping ()
- void reboot (unsigned char id)
- void factory_reset (unsigned char id, int option)
- unsigned char read_byte (unsigned char id, int address)
- void write byte (unsigned char id, int address, unsigned char value)
- unsigned short read_word (unsigned char id, int address)
- void write_word (unsigned char id, int address, unsigned short value)
- unsigned long read_dword (unsigned char id, int address)
- void write_dword (unsigned char id, int address, unsigned long value)
- unsigned char get_bulk_read_data_byte (unsigned char id, unsigned int start_address)
- unsigned short get_bulk_read_data_word (unsigned char id, unsigned int start_address)
- unsigned long get bulk read data dword (unsigned char id, unsigned int start address)
- unsigned char **get sync read data byte** (unsigned char id, unsigned int start address)
- unsigned short get_sync_read_data_word (unsigned char id, unsigned int start_address)
- unsigned long get_sync_read_data_dword (unsigned char id, unsigned int start_address)
- void add_stuffing()
- void remove_stuffing ()
- double get_packet_time ()
- int is_packet_timeout ()
- · void set packet timeout (int NumRcvByte)
- void set packet timeout ms (int msec)

The documentation for this class was generated from the following files:

- · dynamixel.h
- · dynamixel.cpp

3.6 XJoystick::Info Struct Reference

Struct to handle the info.

#include <xjoystick.h>

Public Member Functions

• Info ()

Default Constructor.

Public Attributes

• int ID

Contains the Joystick's ID.

· QString name

Contains all the data.

3.6.1 Detailed Description

Struct to handle the info.

The documentation for this struct was generated from the following file:

xjoystick.h

8 Class Documentation

3.7 MainWindow Class Reference

Inheritance diagram for MainWindow:

Collaboration diagram for MainWindow:

Public Member Functions

• MainWindow (QWidget *parent=0)

Default constructor.

∼MainWindow ()

Default destructor.

The documentation for this class was generated from the following files:

- · mainwindow.h
- · mainwindow.cpp

3.8 OptionsServos Class Reference

Inheritance diagram for OptionsServos:

Collaboration diagram for OptionsServos:

Public Member Functions

• OptionsServos (QWidget *parent=0)

The documentation for this class was generated from the following files:

- · optionsservos.h
- · optionsservos.cpp

3.9 OptionsWindow Class Reference

Inheritance diagram for OptionsWindow:

Collaboration diagram for OptionsWindow:

Public Member Functions

• OptionsWindow (QWidget *parent=0)

The documentation for this class was generated from the following files:

- · optionswindow.h
- · optionswindow.cpp

3.10 ping_data Struct Reference

Public Attributes

- int iID
- int iModelNo
- · int iFirmVer

The documentation for this struct was generated from the following file:

· dynamixel.h

3.11 XJoystick Class Reference

The XJoystick's class is used to control the SFML Joystick's class with signals and slots

```
#include <xjoystick.h>
```

Inheritance diagram for XJoystick:

Collaboration diagram for XJoystick:

Classes

struct Info

Struct to handle the info.

Public Slots

• void update ()

Updates all data.

Signals

• void changed ()

Emmitted when a joystick is connected or disconnected.

Public Member Functions

• XJoystick (int ID=-1, float filter=0.001)

Default constructor.

∼XJoystick ()

Default destructor.

• int amount ()

Amount of joysticks connected.

• bool anyConnected ()

True if there's any joystick connected.

QVector< Info > available ()

Returns the system available joysticks.

• bool button (int n)

Returns the button state.

10 Class Documentation

• int buttonCount ()

Returns the number of buttons.

- int current ()
- QVector< P > getAxis ()

Returns all the Joystick's axis and it's names.

• void axisPress (unsigned char a, float value=100)

To mantain an axis in a certain value.

• void axisRelease (unsigned char a)

To release an axis and restore it's value with the joystick.

• const float & operator[] (int n) const

Returns the 'n' axis value.

• bool select (int s)

Selects the especified joystick.

3.11.1 Detailed Description

The XJoystick's class is used to control the SFML Joystick's class with signals and slots

3.11.2 Member Function Documentation

```
3.11.2.1 int XJoystick::current() [inline]
```

Returns the current selected joystick, -1 if there's no selected joystick

The documentation for this class was generated from the following files:

- · xjoystick.h
- · xjoystick.cpp

Index

AX12, 5
current XJoystick, 10
data, 5 dxl_hal, 5 dynamixel, 6 dynamixel2, 6
MainWindow, 8
OptionsServos, 8 OptionsWindow, 8
ping_data, 9
XJoystick, 9 current, 10 XJoystick::Info, 7